Computer Networks

Prof. Dr. Hasan Hüseyin BALIK

(5th, 6th and 7th Weeks)

3. Transport Layer

• • •

Transport layer: overview

Our goal:

- understand principles behind transport layer services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control

- learn about Internet transport layer protocols:
 - UDP: connectionless transport
 - TCP: connection-oriented reliable transport
 - TCP congestion control


Transport layer: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality




Transport services and protocols

- provide logical communication between application processes running on different hosts
- transport protocols actions in end systems:
 - sender: breaks application messages into segments, passes to network layer
 - receiver: reassembles segments into messages, passes to application layer
- two transport protocols available to Internet applications
 - TCP, UDP



Transport vs. network layer services and protocols



household analogy:

- 12 kids in Ann's house sending letters to 12 kids in Bill's house:
- hosts = houses
- processes = kids
- app messages = letters in envelopes


Transport vs. network layer services and protocols

- network layer: logical communication between hosts
- transport layer: logical communication between processes
 - relies on, enhances, network layer services

household analogy:


- 12 kids in Ann's house sending letters to 12 kids in Bill's house:
- hosts = houses
- processes = kids
- app messages = letters in envelopes

Transport Layer Actions




Sender:

- is passed an applicationlayer message
- determines segment header fields values
- creates segment
- passes segment to IP




Transport Layer Actions




Receiver:

- receives segment from IP
- checks header values
- extracts application-layer message
- demultiplexes message up to application via socket



Two principal Internet transport protocols


- **TCP:** Transmission Control Protocol
 - reliable, in-order delivery
 - congestion control
 - flow control
 - connection setup
- UDP: User Datagram Protocol
 - unreliable, unordered delivery
 - no-frills extension of "best-effort" IP
- services not available:
 - delay guarantees
 - bandwidth guarantees





Chapter 3: roadmap


- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality




























Multiplexing/demultiplexing



How demultiplexing works

- host receives IP datagrams
 - each datagram has source IP address, destination IP address
 - each datagram carries one transport-layer segment
 - each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

Connectionless demultiplexing

Recall:

when creating socket, must specify *host-local* port #:

- when creating datagram to send into UDP socket, must specify
 - destination IP address
 - destination port #

when receiving host receives *UDP* segment:


- checks destination port # in segment
- directs UDP segment to socket with that port #



IP/UDP datagrams with same dest.

port #, but different source IP
addresses and/or source port
numbers will be directed to same
socket at receiving host

Connectionless demultiplexing: an example




Connection-oriented demultiplexing

- TCP socket identified by 4-tuple:
 - source IP address
 - source port number
 - dest IP address
 - dest port number
- demux: receiver uses all four values (4-tuple) to direct segment to appropriate socket

- server may support many simultaneous TCP sockets:
 - each socket identified by its own 4-tuple
 - each socket associated with a different connecting client

Connection-oriented demultiplexing: example



Three segments, all destined to IP address: B,

dest port: 80 are demultiplexed to different sockets

Transport layer: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



UDP: User Datagram Protocol

- "no frills," "bare bones"
 Internet transport protocol
- "best effort" service, UDP segments may be:
 - lost
 - delivered out-of-order to app
- connectionless:
 - no handshaking between UDP sender, receiver
 - each UDP segment handled independently of others

Why is there a UDP?

- no connection establishment (which can add RTT delay)
- simple: no connection state at sender, receiver
- small header size
- no congestion control
 - UDP can blast away as fast as desired!
 - can function in the face of congestion

UDP: User Datagram Protocol

- UDP use:
 - streaming multimedia apps (loss tolerant, rate sensitive)
 - DNS
 - SNMP
 - HTTP/3
- if reliable transfer needed over UDP (e.g., HTTP/3):
 - add needed reliability at application layer
 - add congestion control at application layer

UDP: User Datagram Protocol [RFC 768]

INTERNET STANDARD

RFC 768

J. Postel ISI 28 August 1980


User Datagram Protocol

Introduction


This User Datagram Protocol (UDP) is defined to make available a datagram mode of packet-switched computer communication in the environment of an interconnected set of computer networks. This protocol assumes that the Internet Protocol (IP) [1] is used as the underlying protocol.

This protocol provides a procedure for application programs to send messages to other programs with a minimum of protocol mechanism. The protocol is transaction oriented, and delivery and duplicate protection are not guaranteed. Applications requiring ordered reliable delivery of streams of data should use the Transmission Control Protocol (TCP) [2].

Format



UDP: Transport Layer Actions



UDP: Transport Layer Actions


SNMP client

application
transport
(UDP)
network (IP)
link
physical

UDP sender actions:


- is passed an applicationlayer message
- determines UDP segment header fields values
- creates UDP segment
- passes segment to IP

SNMP server



UDP: Transport Layer Actions


SNMP client




UDP receiver actions:

- receives segment from IP
- checks UDP checksum header value
- extracts application-layer message
- demultiplexes message up to application via socket

SNMP server




UDP segment header



UDP checksum

Goal: detect errors (i.e., flipped bits) in transmitted segment



UDP (Internet) checksum

Goal: detect errors (i.e., flipped bits) in transmitted segment

sender:


- treat contents of UDP segment (including UDP header fields and IP addresses) as sequence of 16-bit integers
- checksum: addition (one's complement sum) of segment content
- checksum value put into UDP checksum field

receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
 - not equal error detected
 - equal no error detected. But maybe errors nonetheless? More later

Internet checksum: an example

example: add two 16-bit integers




Note: when adding numbers, a carryout from the most significant bit needs to be added to the result

^{*} Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive/

Internet checksum: weak protection!

example: add two 16-bit integers



Transport layer: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality




Principles of reliable data transfer



reliable service abstraction


Principles of reliable data transfer



reliable service implementation

Principles of reliable data transfer

Complexity of reliable data transfer protocol will depend (strongly) on characteristics of unreliable channel (lose, corrupt, reorder data?)




reliable service *implementation*


Principles of reliable data transfer

Sender, receiver do *not* know the "state" of each other, e.g., was a message received?

unless communicated via a message




Reliable data transfer protocol (rdt): interfaces



Reliable data transfer: getting started

We will:


- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- consider only unidirectional data transfer
 - but control info will flow in both directions!
- use finite state machines (FSM) to specify sender, receiver




rdt1.0: reliable transfer over a reliable channel

- underlying channel perfectly reliable
 - no bit errors
 - no loss of packets
- separate FSMs for sender, receiver:
 - sender sends data into underlying channel
 - receiver reads data from underlying channel







rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
 - checksum (e.g., Internet checksum) to detect bit errors
- *the* question: how to recover from errors?


How do humans recover from "errors" during conversation?

rdt2.0: channel with bit errors


- underlying channel may flip bits in packet
 - checksum to detect bit errors
- *the* question: how to recover from errors?
 - acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
 - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
 - sender *retransmits* pkt on receipt of NAK

stop and wait
 sender sends one packet, then waits for receiver response

rdt2.0: FSM specifications



rdt2.0: FSM specification




Note: "state" of receiver (did the receiver get my message correctly?) isn't known to sender unless somehow communicated from receiver to sender


that's why we need a protocol!



rdt2.0: operation with no errors



rdt2.0: corrupted packet scenario



rdt2.0 has a fatal flaw!

what happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate


handling duplicates:

- sender retransmits current pkt if ACK/NAK corrupted
- sender adds sequence number to each pkt
- receiver discards (doesn't deliver up) duplicate pkt


stop and wait

sender sends one packet, then waits for receiver response

rdt2.1: sender, handling garbled ACK/NAKs



rdt2.1: receiver, handling garbled ACK/NAKs



rdt2.1: discussion

sender:

- seq # added to pkt
- two seq. #s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
 - state must "remember" whether "expected" pkt should have seq # of 0 or 1

receiver:


- must check if received packet is duplicate
 - state indicates whether 0 or 1 is expected pkt seq #
- note: receiver can not know if its last ACK/NAK received OK at sender

rdt2.2: a NAK-free protocol

- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
 - receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt

As we will see, TCP uses this approach to be NAK-free

rdt2.2: sender, receiver fragments



rdt3.0: channels with errors and loss

New channel assumption: underlying channel can also lose packets (data, ACKs)

checksum, sequence #s, ACKs, retransmissions will be of help ...
 but not quite enough

Q: How do *humans* handle lost sender-to-receiver words in conversation?


rdt3.0: channels with errors and loss

Approach: sender waits "reasonable" amount of time for ACK


- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
 - retransmission will be duplicate, but seq #s already handles this!
 - receiver must specify seq # of packet being ACKed
- use countdown timer to interrupt after "reasonable" amount of time

timeout


rdt3.0 sender




rdt3.0 sender





rdt3.0 in action





rdt3.0 in action






(d) premature timeout/ delayed ACK

Performance of rdt3.0 (stop-and-wait)

- *U* _{sender}: *utilization* fraction of time sender busy sending
- example: 1 Gbps link, 15 ms prop. delay, 8000 bit packet
 - time to transmit packet into channel:

$$D_{trans} = \frac{L}{R} = \frac{8000 \text{ bits}}{10^9 \text{ bits/sec}} = 8 \text{ microsecs}$$

rdt3.0: stop-and-wait operation



rdt3.0: stop-and-wait operation

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R}$$

$$= \frac{.008}{30.008}$$


$$= 0.00027$$

- rdt 3.0 protocol performance stinks!
- Protocol limits performance of underlying infrastructure (channel)

rdt3.0: pipelined protocols operation


pipelining: sender allows multiple, "in-flight", yet-to-be-acknowledged packets

- range of sequence numbers must be increased
- buffering at sender and/or receiver




(a) a stop-and-wait protocol in operation

Pipelining: increased utilization



Go-Back-N: sender

- sender: "window" of up to N, consecutive transmitted but unACKed pkts
 - k-bit seq # in pkt header




- cumulative ACK: ACK(n): ACKs all packets up to, including seq # n
 - on receiving ACK(n): move window forward to begin at n+1
- timer for oldest in-flight packet
- timeout(n): retransmit packet n and all higher seq # packets in window

Go-Back-N: receiver

- ACK-only: always send ACK for correctly-received packet so far, with highest in-order seq #
 - may generate duplicate ACKs
 - need only remember rcv base
 - on receipt of out-of-order packet:
 - can discard (don't buffer) or buffer: an implementation decision
 - re-ACK pkt with highest in-order seq #

Receiver view of sequence number space:




received and ACKed

Out-of-order: received but not ACKed

Not received


Go-Back-N in action



Selective repeat

- receiver individually acknowledges all correctly received packets
 - buffers packets, as needed, for eventual in-order delivery to upper layer
- sender times-out/retransmits individually for unACKed packets
 - sender maintains timer for each unACKed pkt
- sender window
 - N consecutive seq #s
 - limits seq #s of sent, unACKed packets

Selective repeat: sender, receiver windows



Selective repeat: sender and receiver

sender

data from above:

if next available seq # in window, send packet

timeout(*n*):

resend packet n, restart timer

ACK(n) in [sendbase,sendbase+N]:

- mark packet n as received
- if n smallest unACKed packet, advance window base to next unACKed seq #

receiver

packet n in [rcvbase, rcvbase+N-1]

- send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order packets), advance window to next not-yetreceived packet


packet n in [rcvbase-N,rcvbase-1]

ACK(n)

otherwise:

ignore


Selective Repeat in action




Selective repeat: a dilemma!

example:

- seq #s: 0, 1, 2, 3 (base 4 counting)
- window size=3






Selective repeat: a dilemma!

example:

- seq #s: 0, 1, 2, 3 (base 4 counting)
- window size=3

Q: what relationship is needed between sequence # size and window size to avoid problem in scenario (b)?



Transport layer: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- Principles of congestion control
- TCP congestion control



TCP: overview RFCs: 793,1122, 2018, 5681, 7323

- point-to-point:
 - one sender, one receiver
- reliable, in-order byte steam:
 - no "message boundaries"
- full duplex data:
 - bi-directional data flow in same connection
 - MSS: maximum segment size

- cumulative ACKs
- pipelining:
 - TCP congestion and flow control set window size
- connection-oriented:
 - handshaking (exchange of control messages) initializes sender, receiver state before data exchange
- flow controlled:
 - sender will not overwhelm receiver

TCP segment structure

32 bits dest port # source port # segment seq #: counting ACK: seq # of next expected bytes of data into bytestream sequence number byte; A bit: this is an ACK (not segments!) acknowledgement number head not CE length (of TCP header) receive window flow control: # bytes Internet checksum receiver willing to accept checksum Urg data pointer options (variable length) C, E: congestion notification TCP options application data sent by RST, SYN, FIN: connection data application into management (variable length) TCP socket

TCP sequence numbers, ACKs

Sequence numbers:


 byte stream "number" of first byte in segment's data

Acknowledgements:


- seq # of next byte expected from other side
- cumulative ACK

Q: how receiver handles out-oforder segments

 A: TCP spec doesn't say, - up to implementor



TCP sequence numbers, ACKs



simple telnet scenario

TCP round trip time, timeout

- Q: how to set TCP timeout value?
- longer than RTT, but RTT varies!
- too short: premature timeout, unnecessary retransmissions
- too long: slow reaction to segment loss


Q: how to estimate RTT?

- SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT

TCP round trip time, timeout

EstimatedRTT = $(1-\alpha)$ *EstimatedRTT + α *SampleRTT

- <u>e</u>xponential <u>w</u>eighted <u>m</u>oving <u>a</u>verage (EWMA)
- influence of past sample decreases exponentially fast
- typical value: α = 0.125



TCP round trip time, timeout

- timeout interval: EstimatedRTT plus "safety margin"
 - large variation in EstimatedRTT: want a larger safety margin

DevRTT: EWMA of SampleRTT deviation from EstimatedRTT:

DevRTT =
$$(1-\beta)$$
*DevRTT + β *|SampleRTT-EstimatedRTT|

(typically, $\beta = 0.25$)

^{*} Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive/

TCP Sender (simplified)

event: data received from application

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
 - think of timer as for oldest unACKed segment
 - expiration interval:TimeOutInterval


event: timeout

- retransmit segment that caused timeout
- restart timer


event: ACK received

- if ACK acknowledges previously unACKed segments
 - update what is known to be ACKed
 - start timer if there are still unACKed segments


TCP Receiver: ACK generation [RFC 5681]



TCP: retransmission scenarios



TCP: retransmission scenarios




TCP fast retransmit

TCP fast retransmit

if sender receives 3 additional ACKs for same data ("triple duplicate ACKs"), resend unACKed segment with smallest seq #

 likely that unACKed segment lost, so don't wait for timeout

Receipt of three duplicate ACKs indicates 3 segments received after a missing segment – lost segment is likely. So retransmit!




Transport layer: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- Principles of congestion control
- TCP congestion control




Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?



receiver protocol stack


Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?






Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?

Application removing data from TCP socket buffers




receiver protocol stack



Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?


-flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast



receiver protocol stack


- TCP receiver "advertises" free buffer space in rwnd field in TCP header
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust
 RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow



TCP receiver-side buffering

- TCP receiver "advertises" free buffer space in rwnd field in TCP header
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust
 RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow

flow control: # bytes receiver willing to accept




TCP segment format

TCP connection management

before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters (e.g., starting seq #s)




```
application


connection state: ESTAB
connection Variables:
seq # client-to-server
server-to-client
rcvBuffer size
at server,client

network
```

Agreeing to establish a connection

2-way handshake:






Q: will 2-way handshake always work in network?


- variable delays
- retransmitted messages (e.g. req_conn(x)) due to message loss
- message reordering
- can't "see" other side

2-way handshake scenarios






2-way handshake scenarios



2-way handshake scenarios



TCP 3-way handshake


Client state

serverSocket.listen(1) clientSocket = socket(AF INET, SOCK STREAM) LISTEN clientSocket.connect((serverName, serverPort) choose init seq num, x send TCP SYN msq **SYNSENT** SYNbit=1, Seq=x choose init seq num, y send TCP SYNACK msg, acking SYN SYNbit=1, Seq=y ACKbit=1; ACKnum=x+1 received SYNACK(x) indicates server is live; **ESTAB** send ACK for SYNACK; this segment may contain ACKbit=1, ACKnum=y+1 client-to-server data received ACK(y) indicates client is live

Server state

```
serverSocket = socket(AF INET, SOCK STREAM)
serverSocket.bind(('', serverPort))
connectionSocket, addr = serverSocket.accept()
                  LISTEN
               SYN RCVD
                   ESTAB
```

A human 3-way handshake protocol



Closing a TCP connection

- client, server each close their side of connection
 - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
 - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

Transport layer: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



Principles of congestion control

Congestion:

• informally: "too many sources sending too much data too fast for network to handle"

- manifestations:
 - long delays (queueing in router buffers)
 - packet loss (buffer overflow at routers)
- different from flow control!
- a top-10 problem!




too many senders, sending too fast


flow control: one sender too fast for one receiver

Simplest scenario:


- one router, infinite buffers
- input, output link capacity: R
- two flows
- no retransmissions needed



Q: What happens as arrival rate λ_{in} approaches R/2?




maximum per-connection throughput: R/2




large delays as arrival rate λ_{in} approaches capacity


- one router, *finite* buffers
- sender retransmits lost, timed-out packet
 - application-layer input = application-layer output: $\lambda_{in} = \lambda_{out}$
 - transport-layer input includes retransmissions : $\lambda'_{in} \ge \lambda_{in}$



Idealization: perfect knowledge


sender sends only when router buffers available






Idealization: some perfect knowledge


- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost



Idealization: some perfect knowledge

- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost







R/2

 λ_{in}

Realistic scenario: *un-needed duplicates*


- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered





Realistic scenario: *un-needed duplicates*

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered





"costs" of congestion:

- more work (retransmission) for given receiver throughput
- unneeded retransmissions: link carries multiple copies of a packet
 - decreasing maximum achievable throughput

- four senders
- multi-hop paths
- timeout/retransmit

- \underline{Q} : what happens as λ_{in} and λ_{in} increase ?
- A: as red λ_{in} increases, all arriving blue pkts at upper queue are dropped, blue throughput \rightarrow 0







another "cost" of congestion:


when packet dropped, any upstream transmission capacity and buffering used for that packet was wasted!


Causes/costs of congestion: insights


- throughput can never exceed capacity
- delay increases as capacity approached
- loss/retransmission decreases effective throughput
- un-needed duplicates further decreases effective throughput
- upstream transmission capacity / buffering wasted for packets lost downstream












Approaches towards congestion control

End-end congestion control:


- no explicit feedback from network
- congestion inferred from observed loss, delay
- approach taken by TCP



Approaches towards congestion control

Network-assisted congestion control:

- routers provide direct feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols



Transport layer: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



TCP congestion control: AIMD

 approach: senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event

Additive Increase <u>Multiplicative Decrease</u> increase sending rate by 1 cut sending rate in half at maximum segment size every each loss event RTT until loss detected Sending rate **AIMD** sawtooth behavior: probing TCP sender for bandwidth

time

TCP AIMD: more


Multiplicative decrease detail: sending rate is

- Cut in half on loss detected by triple duplicate ACK (TCP Reno)
- Cut to 1 MSS (maximum segment size) when loss detected by timeout (TCP Tahoe)

Why AIMD?

- AIMD a distributed, asynchronous algorithm has been shown to:
 - optimize congested flow rates network wide!
 - have desirable stability properties

TCP congestion control: details



TCP sending behavior:


 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

TCP rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

- TCP sender limits transmission: LastByteSent- LastByteAcked < cwnd
- cwnd is dynamically adjusted in response to observed network congestion (implementing TCP congestion control)

TCP slow start

- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = 1 MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- summary: initial rate is slow, but ramps up exponentially fast




TCP: from slow start to congestion avoidance

Q: when should the exponential increase switch to linear?

A: when **cwnd** gets to 1/2 of its value before timeout.


Implementation:

- variable ssthresh
- on loss event, ssthresh is set to
 1/2 of cwnd just before loss event




^{*} Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive/

Summary: TCP congestion control




TCP CUBIC

- Is there a better way than AIMD to "probe" for usable bandwidth?
- Insight/intuition:
 - W_{max}: sending rate at which congestion loss was detected
 - congestion state of bottleneck link probably (?) hasn't changed much
 - after cutting rate/window in half on loss, initially ramp to to W_{max} faster, but then approach W_{max} more slowly




TCP CUBIC

- K: point in time when TCP window size will reach W_{max}
 - K itself is tuneable
- increase W as a function of the cube of the distance between current time and K
 - larger increases when further away from K
 - smaller increases (cautious) when nearer K
- TCP CUBIC default in Linux, most popular TCP for popular Web servers




TCP and the congested "bottleneck link"

 TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the bottleneck link




TCP and the congested "bottleneck link"

- TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the bottleneck link
- understanding congestion: useful to focus on congested bottleneck link



Delay-based TCP congestion control

Keeping sender-to-receiver pipe "just full enough, but no fuller": keep bottleneck link busy transmitting, but avoid high delays/buffering



Delay-based approach:

- RTT_{min} minimum observed RTT (uncongested path)
- uncongested throughput with congestion window cwnd is cwnd/RTT_{min}

```
if measured throughput "very close" to uncongested throughput increase cwnd linearly /* since path not congested */ else if measured throughput "far below" uncongested throughout decrease cwnd linearly /* since path is congested */
```


Delay-based TCP congestion control

- congestion control without inducing/forcing loss
- maximizing throughout ("keeping the just pipe full...") while keeping delay low ("...but not fuller")
- a number of deployed TCPs take a delay-based approach
 - BBR deployed on Google's (internal) backbone network

Explicit congestion notification (ECN)


TCP deployments often implement *network-assisted* congestion control:

- two bits in IP header (ToS field) marked by network router to indicate congestion
 - policy to determine marking chosen by network operator
- congestion indication carried to destination
- destination sets ECE bit on ACK segment to notify sender of congestion
- involves both IP (IP header ECN bit marking) and TCP (TCP header C,E bit marking)



TCP fairness


Fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



Q: is TCP Fair?

Example: two competing TCP sessions:

- additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



Is TCP fair?

A: Yes, under idealized assumptions:

- same RTT
- fixed number of sessions only in congestion avoidance

Fairness: must all network apps be "fair"?

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- instead use UDP:
 - send audio/video at constant rate, tolerate packet loss
- there is no "Internet police" policing use of congestion control

Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this, e.g., link of rate R with 9 existing connections:
 - new app asks for 1 TCP, gets rate R/10
 - new app asks for 11 TCPs, gets R/2

Transport layer: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



Evolving transport-layer functionality


- TCP, UDP: principal transport protocols for 40 years
- different "flavors" of TCP developed, for specific scenarios:

Scenario	Challenges
Long, fat pipes (large data	Many packets "in flight"; loss shuts down
transfers)	pipeline
Wireless networks	Loss due to noisy wireless links, mobility;
	TCP treat this as congestion loss
Long-delay links	Extremely long RTTs
Data center networks	Latency sensitive
Background traffic flows	Low priority, "background" TCP flows

- moving transport—layer functions to application layer, on top of UDP
 - HTTP/3: QUIC

QUIC: Quick UDP Internet Connections

- application-layer protocol, on top of UDP
 - increase performance of HTTP
 - deployed on many Google servers, apps (Chrome, mobile YouTube app)




QUIC: Quick UDP Internet Connections

adopts approaches we've studied in this presentation for connection establishment, error control, congestion control


- error and congestion control: "Readers familiar with TCP's loss detection and congestion control will find algorithms here that parallel well-known TCP ones." [from QUIC specification]
- connection establishment: reliability, congestion control, authentication, encryption, state established in one RTT
- multiple application-level "streams" multiplexed over single QUIC connection
 - separate reliable data transfer, security
 - common congestion control

QUIC: Connection establishment



TCP (reliability, congestion control state) + TLS (authentication, crypto state)


2 serial handshakes



QUIC: reliability, congestion control, authentication, crypto state

1 handshake

QUIC: streams: parallelism, no HOL blocking



(a) HTTP 1.1